Ap PDF Split/Merge
User manual
(Support command line)

Introduction

PDF Split Merge is a stand-alone tool for splitting, merging PDF documents,allows you to
split large PDF files into smaller PDF files,and merge one or more PDF files.
PDF Split Merge is offered as an easy-to-use GUI (Graphical User Interface) application, and command-line application.
The split functionality lets you split one or more PDF files based on page groups, page ranges.
The merge functionality lets you quickly combine a collection of PDF documents and page sets.

Features

Adobe Acrobat and Reader NOT required!
Automates the process of splitting and merging multiple PDF files
Rearrange pages in a document
Split PDF documents by page numbers or custom page ranges etc
Split a file into single pages or sets of pages
Merging one or more PDF files
Many different split and merge methods
Supports Command Line and batch processing
Supports Win98,ME,NT4,Windows 2000&XP&2003
Drag and Drop support of files
List order organizing
Save, Load & Append Batch Lists
Modify document information data such as Author, Subject, Title or Keywords to all generated documents.

Limitations in the trial version
        Insert a watermark string in the every page in the PDF file

Getting Started
        1. Registration Window

The demo version of PDF Split/Merge software is a fully functional product with all features required for testing
available. After you are convinced that the program fits your needs, you are strongly encouraged to purchase and
register your copy of the software by acquiring a personal unlock key, the demo version has watermark in the
generated PDF file.

In your evaluate period, you may click "Try" button to try this software.

2. PDF Split

  This feature enables you to split single or multiple PDF document.

Buttons:

 Add PDF Files: Add PDF documents into the File List
 Add Directory: Add all PDF documents in a folder into the File List
 Start Split: Start to Split PDF file(s) in the File List

Split files list columns description:

         Source File: be split of pdf files,include path, e.g. C:\pdf\input.pdf
         Pages: page numbers of pdf file
         Split Parameters: indicate extract pages of ranges from a PDF file,
                                 e.g. 1,3;5-10;2,4,6,8-10 or Into Single Page, see follow table.
         Destination Folder: save destination file of folder, e.g. C:\aaa\
         Output Base: output file base name

  Example:
         if Source File is c:\pdf\input.pdf , Pages is 10 ,
            Split Parameters is 1,3;5-10;2,4,6,8-10 ,
            Destination Folder is C:\aaa\ ,
            Output Base is output ,
         then result is:
            c:\aaa\output01.pdf   the file content include page1 and page 3.
            c:\aaa\output02.pdf   the file content include 5-10 of page.
            c:\aaa\output03.pdf   the file content include page2,4,5,8,9,10.

 PDF Split allows operation of individual pages, page ranges and page sets, For example:

Split Parameters Description
 Into Single Page It will split the document into single pages.
2 Extract page number 2 into a new document.
2,7 Extract pages 2 and 7 into a new document.

1-9 Create a single output file containing pages 1 through 9.
8;9 Extract pages 8 and 9 into two separate files

3. PDF Merge

Supports document merging through its 'PDF Merge' tab.

Buttons:

Add PDF Files: Add PDF documents into the File List
Add Directory: Add all PDF documents in a folder into the File List
Start Merge: Start to Merge PDF file(s) in the File List

Merge files list columns description:

Source File: be merge of pdf files,include path, e.g. C:\pdf\input.pdf
Pages: page numbers of pdf file
Merge Parameters: indicate extract pages of ranges from a PDF file,
                           e.g. 1,3;5-10;2,4,6,8-10 or All Pages, see follow table.
Destination File: save a new merge file, include path, e.g. C:\aaa\merge.pdf

Example:
if   Source File is c:\pdf\input1.pdf , Pages is 10 , Merge Parameters is All Pages
     Destination Folder is C:\aaa\merge.pdf , and
     Source File is c:\pdf\input2.pdf , Pages is 20 , Merge Parameters is All Pages
     Destination Folder is C:\aaa\merge.pdf
then result is:
     c:\aaa\merge.pdf   The file contain both input1.pdf and input2.pdf

PDF Merge allows operation of individual pages, page ranges and page sets, For example:

Merge Parameters Description
All Pages It will merge the document all page to a new document.
2 Extract page number 2 into a new merge document.
2,7 Extract pages 2 and 7 into a new merge document.
1-9 Extract pages 1 through 9 into a new merge document.

4. Default Options

Default Split Page Range
    Be used for default value of the split list Split Parameters .

Default Merge Page Range
    Be used for default value of the merge list Split Parameters .

Default Output
    Split Destination Folder: The split list Destination Folder default value
    Split Output Base   :   The split list Output Base default value
    Merge Destination File : The merge list Destination File default value

Other
    View After Split/Merge
    Show Log File After Split/Merge

 Ap PDF Split/Merge Contact
    Info page
    http://www.adultpdf.com/products/pdfsplitmerge/index.html
    http://www.adultpdf.com/products/pdfsplitmerge/help.html
    Order page
    http://www.regsoft.net/purchase.php3?productid=69248

    Web site (more other software)
    http://www.adultpdf.com

  Technical Support and Freeback
    If you have any technical questions, suggests, bug reports, please contact us at support@adultpdf.com
    If you have ideas and suggestions on how we could improve PDF Split/Merge, we would love to hear your thoughts.
    Please send them to support@adultpdf.com